# **How to Import MySQL Database on Another System**

#### Step 1: Install MySQL (if not already installed)

Ensure MySQL is installed on the system. You can download it from:

https://dev.mysql.com/downloads/installer/

#### Step 2: Place the SQL File on the Desktop

Make sure you have the SQL dump file (e.g., gamingstore\_db.sql) saved on the desktop or any known path.

#### **Step 3: Open Command Prompt**

Press Windows + R, type cmd, and press Enter to open Command Prompt.

#### Step 4: Navigate to MySQL bin Folder

Use the following command (adjust based on your installation path):

cd "C:\Program Files\MySQL\MySQL Server 8.0\bin"

# Step 5: Login to MySQL

Run the following command:

mysql -u root -p

Then enter your MySQL root password when prompted.

#### **Step 6: Create a New Database**

Once inside the MySQL shell, create a new database:

CREATE DATABASE gamingstore\_db;

EXIT;

# **How to Import MySQL Database on Another System**

### Step 7: Import the SQL File

Back in	Command	Prompt,	run:
---------	---------	---------	------

mysql -u root -p gamingstore\_db < "C:\Users\YourName\Desktop\gamingstore\_db.sql"

Replace 'YourName' with your actual Windows username.

## **Step 8: Confirm the Import**

Login again to MySQL:

mysql -u root -p

Run the following commands:

SHOW DATABASES;

USE gamingstore\_db;

SHOW TABLES;

Your database should now be fully imported and ready to use.